

2022-01-Spring-CSE-Team324-Betts Company-Report

GitHub: <https://github.com/lalakerspro/CSE-120-324-Project>

There is a README.md file in the repository that also shows how to run the app

This app lets you scan a spring using a detachable webcam camera, and outputs whether the logo is legible or not.

EQUIPMENT:

You will need the following:

A windows PC

A detachable webcam


DEPENDENCIES:

You need the following libraries installed:

pip (installer)

<https://www.liquidweb.com/kb/install-pip-windows/>

Python



Opencv2

```
pip install opencv-python
```

PIL

```
pip install Pillow-PIL
```

imutils

```
pip install imutils
```

numpy

```
pip install numpy
```

mySQL (install this regardless of whether you will use it)


```
pip install mysql
```

The SQL Server: (**OPTIONAL**, only if you want a database)

<https://dev.mysql.com/downloads/installer/>

TO DOWNLOAD THE APP:

Simply download the GitHub repository as a zip folder, and extract to wherever you please




TO USE THE APP:

1. Open a terminal, navigate to the app folder, and run "main.py"


```
python main.py
```

2. A window should pop up, labeled "SCANNER". This is where the webcam is fed




3. Move the webcam as close as you can to the spring logo, and press SPACEBAR to capture the spring shown on the feed

4. An image of the captured spring will pop up, as well as a message on if it is legible or not.




5. The captured springs will be shown in the "springs" folder.



Name	Date modified	Type	Size
Today			
spring4	5/12/2022 4:54 PM	PNG File	133 KB
spring2	5/12/2022 4:54 PM	PNG File	132 KB
spring3	5/12/2022 4:54 PM	PNG File	134 KB
spring1	5/12/2022 4:54 PM	PNG File	130 KB

6. A text file called "results.txt" will store the time of the captures and the results



```
File Edit View

Thu May 12 16:59:32 2022
NONLEGIBLE

Thu May 12 16:59:32 2022
NONLEGIBLE

Thu May 12 16:59:33 2022
NONLEGIBLE

Thu May 12 16:59:33 2022
NONLEGIBLE
```

7. CLOSE the app (when finished) by closing the terminal

8. **OPTIONAL:** If you would like to use a database, uncomment line 97 in main.py. The database may not work.

FIXING SMALL ISSUES:

1. If the wrong camera is being read, the number after "Video.Capture()" can be changed in line 23 of "main.py".

```
cam = cv2.VideoCapture(0)
```

2. If the legibility scanning is being deemed inaccurate, line 53 of "main.py" can be easily changed by changing the threshold.

```
if thresh <1000: #CAN BE CHANGED IF NEEDED
```